

Pair Strength Analyzer (PSA)

This is an indicator that I used as an adjunct to my strength indicators, to confirm strength/weakness by using a very different algorithm. I've finally decided to share it publicly. There is nothing magical about it; it is merely another way of calculating trend strength, and — as always — the question is whether the trend (on your chosen timeframe/horizon) remains effective, on average, for long enough for you to profit from it. The indicator ranks currencies, from the strongest trending down to the most sideways moving, according to the parameter settings that you decide to apply.

The indicator was written and compiled using MT4 build 509. I have no idea whether it will work correctly on build 600 or later.

TERMS AND CONDITIONS


Please note that all code in this thread is supplied FREE of charge. Therefore the following conditions apply:

1. You agree that, if you download and use the code, it is **ENTIRELY AT YOUR OWN RISK**. I accept **NO LIABILITY** for any financial losses or computer related damage, caused by either the correct or incorrect use of the code.
2. Feel welcome to share the code freely, and modify any MQ4 source. However, you may **NOT** sell, or otherwise distribute, **any part of the code** commercially, without my prior written consent.
3. The code may not run correctly on Windows 7, Windows 8 or Vista, probably for the reasons given here:
<http://4xtrader.net/how-to-run-metatrader-on-windows-7-or-vista/>
4. I'm sorry, but due to my current work commitments, **I am no longer modifying code to suit people's personal requirements, nor posting replies to individual questions in this thread**. (If you can't get the code to work, you may find solutions already posted somewhere in the thread; otherwise, you'll need to find another indicator).

METHODOLOGY

PSA determines trend strength by calculating a weighted average of the slopes of a number of (invisible) regression lines. In each of the screenshots below, I have manually plotted 4 regression lines of different lengths: 25 candle (yellow), 50 candle (magenta), 100 candle (orange) and 200 candle (blue).

In the following screenshot (AUDUSD, H1), both AUD and USD are strong, i.e. positively correlated, resulting in a sideways or 'trendless' chart. The directions/slopes of the 4 regression lines are conflicting and scattered, and averaging their slopes will result in a low summary value (close to zero), as the directions cancel each other.



In the next screenshot (USDJPY,H1), USD is strong and JPY weak, i.e. negative correlation, resulting in a strongly uptrending chart. The directions/slopes of the 4 regression lines are all pointing upward, and averaging their slopes will result in a high positive summary value, as the directions reinforce each other.

(Conversely, in a strongly downtrending chart, the directions of the regression lines would all point downward, and averaging their slopes would result in a high negative summary value).




Custom Indicator - Pair Strength Analyzer

Common Inputs Colors Visualization

Variable	Value
ab CurrencyPairs	GU,UJ,EU,UJ,UC,NU,AU,AN,AC,AF,AJ,CJ,FJ,EG,EA,EF,...
ab SymbolSuffix	
123 ShowTopKPairs	99
ab LengthsForRegr	150,300,600,1200
ab PeriodsForRegr	+0
ab WeightsForRegr	1
123 RescaleUsingATR	100
ab PeriodForATR	+0
UseDollarValueNotPips	false
FinalScaleValue	100.0
123 PrevValuesToDisplay	2
ResetPrevValues	false
123 HistogramWidth	99
ab RefreshPeriod	+0
ab FontNameAndSize	Lucida Console,14
FontColorBullish	LimeGreen
FontColorBearish	Tomato
ab WindowCornerHposVposVspacing	0,TR,10,250,16
ab Visibility	M1,M5,M15,M30,H1,H4,D1,w1,MN
ab OutputFile	PSA.CSV
ShowCcySummary	true

OK Cancel Reset

PAIR STRENGTH ANALYZER



1.31923

1.31923

PARAMETERS

```
extern string CurrencyPairs =  
"GU,UF,EU,UJ,UC,NU,AU,AN,AC,AF,AJ,CJ,FJ,EG,EA,EF,EJ,EN,EC,GF,GA,GC,GJ,GN,NJ,NC,CF,NF";
```

Enter up to 99 currency pair symbols, or abbreviations, separated by commas. In typing the symbol, upper/lowercase may be used interchangeably (e.g. USD or usd).

Permissible abbreviations are: A=AUD; C=CAD; E=EUR; F=CHF; G=GBP; J=JPY; N=NZD; U=USD; H=HKD; S=SGD; Z=ZAR. So you could type G or g instead of GBP, for example. If the currency name typed is not exactly 1 character, the abbreviation will not be recognized.

You can include metals like XAUUSD or XAGUSD in the list. However, depending on how your broker prices these, you may need to use the *RescaleUsingATR* parameter to standardize the result with the currencies.

```
extern string SymbolSuffix = "";
```

Use this if your broker uses symbols like USDJPYm (in which case you would type m here). The suffix you enter will be appended to all symbols you entered in *CurrencyPairs*. Otherwise simply leave the setting blank.

```
extern int ShowTopXPairs = 99;
```

This is the number of strongest trending pairs that you want to be displayed. Leaving the default of 99 means that all pairs will be displayed.

```
extern string LengthsForRegr = "5,10,20,50,125,250,500";
```

These are the lengths (number of candles, counting back from the rightmost candle) of the regression lines whose slopes will be averaged. You may make up to 50 entries here, separated by commas. The default setting means that the average slope of 7 regression lines will be used, of length 5,10,20,50,125,250,500. If you wish to add weight to a particular length, type its number multiple times (e.g. typing it twice gives it double the weight, three times triple the weight, and so on).

By having several different regressions of similar length (e.g. 5,10,15,20,25,30,35,40), the summary value displayed by the indicator will factor in the smoothness (consistency), as well as the overall strength, of the trend.

```
extern string PeriodsForRegr = "+0";
```

You can also have the regression lines repeat themselves over multiple timeframes. You can either enter timeframes as relative to the current chart, separated by commas, i.e. +0 is the current timeframe (**note: be sure to type the + sign**), +1 is the next longer timeframe, +2 is the next longer timeframe after that, etc; -1 is the next shorter timeframe, -2 is the next shorter timeframe, etc. For example, if you're on a H1 chart, and you enter -1,+0,+1, then the slope of 21 regression lines would be averaged, i.e. lines of length 5,10,20,50,125,250,500 on each of the M30, H1 and H4 timeframes. But then if you were to switch to the M15 chart, the slopes of lines of length 5,10,20,50,125,250,500 on each of the M5, M15 and M30 timeframes would all be averaged.

Alternatively, you can enter absolute timeframes like H1, H4, D1 (upper or lowercase). Then these timeframes will be used no matter what the timeframe of the currently displayed chart is, i.e. they remain 'locked' if you switch timeframes.

```
extern string WeightsForRegr = "1";
```

This allows you to specify different weights for each of the corresponding timeframes in *PeriodsForRegr*. For example, if *PeriodsForRegr* is H1, H4 and *WeightsForRegr* is 3,1 then the H1 regression slopes will be weighted 3 times as highly as the H4 regression slopes, when the overall averaging is performed.

The *PeriodsForRegr* and *WeightsForRegr* allow you to create a summary of each pair's strength, into a single value, weighted over any or all of the 9 timeframes available in MT4 (M1,M5,M15,M30,H1,H4,D1,W1,MN), however you wish.

```
extern int RescaleUsingATR = 100;
```

You can re-scale all of the averaged values by entering a positive (>0) here, which will be the ATR (MT4's built-in average true range function) used. For example, if you use the default value of 100, then each slope value will be divided by a 100 period ATR, before they are summed and averaged. This ensures standardization of different units, e.g. pips, points, across different instrument types (currencies, metals, etc).

If you enter 0 (or a negative value), then no re-scaling will be performed, i.e. the 'raw' value of each slope will be used in the averaging process.

```
extern string PeriodForATR = "+0";
```

This is the timeframe that will be used in conjunction with the *RescaleUsingATR* process. You can enter either a relative or absolute value, exactly for *PeriodsForRegr*. Hence if you were to enter D1 here, and set *RescaleUsingATR* to 20, then each slope value would be divided by the pair's 20 day ATR before being passed to the averaging process. If *RescaleUsingATR* is set to 0, then this parameter is ignored.

```
extern bool UseDollarValueNotPips = false;
```

If set to TRUE, this will cause all of the slope values to be multiplied by the 'dollar per pip' ('tickvalue' in MT4 terminology) before the averaging process takes place. Hence the end result will compare dollar values rather than pips. To make this meaningful, this assumes that you have set *RescaleUsingATR* to 0.

If set to FALSE, the raw pip based slope values are passed on to the averaging process.

```
extern double FinalScaleValue = 100;
```

After the weighted averages (summary values) for each pair have been calculated, you can further have these scaled so that the strongest trending pair has a value of 100, and then all other pair's summary values are ratioed down accordingly. Arguably keeps things neat, especially if you are making comparisons of different instances of the indicator with different regression settings.

```
extern int      PrevValuesToDisplay      = 0;
extern bool     ResetPrevValues          = false;
```

In addition to the indicator plotting the current summary values, you can also have the indicator plot up to 2 prior historical values (the summary values are recalculated and redisplayed periodically, according to the *RefreshPeriod* setting). *PrevValuesToDisplay* may have a value of 0, 1 or 2, depending on how many prior values you wish to display, each in a separate column. For example, if the *RefreshPeriod* is M30, then every 30 minutes the previous#2 value disappears, the previous#1 value becomes the new previous#2 value, the current value becomes the new previous#1 value, and a new current value is calculated, as the new M30 candle forms. The current and prior values are all stored in Global Variables, which means that they should remain 'sticky' if MT4 is re-started. If you want to reset all prior values to their current values, set *ResetPrevValues* to TRUE.

New feature: you can set *PrevValuesToDisplay* to -1 or -2. This likewise displays 1 or 2 prior historical values, but the values displayed are the increase (positive value) or decrease (negative value) from the previous value, as opposed to the previous value itself.

```
extern string   HistWidthSymbolSizeOffset = "0,167,10,140";
```

The indicator can also plot a histogram of the summary values. The 4 integer values, separated by commas, are (from left to right):

1. Enter a value between 10 and 60 to set the maximum width (number of bars). The largest value (at the top of the list of pairs) will plot this number of bars, and all lower values will be scaled accordingly. To disable the plotting of the histogram, set this to 0 (or simply blank out the whole parameter).
2. The value of the Wingdings symbol code you want plotted, for each histogram bar. Refer to the Wingdings symbol chart below, and enter its numerical value.
3. The size of the Wingdings font to be used.
4. Sets the number of pixels away from the pair id that the first histogram bar will display. Increasing this value will create a larger gap between the pair id and the histogram.

```
extern string   RefreshPeriod            = "+0";
```

This controls how often the summary values are recalculated and redisplayed. You can enter either a relative or absolute timeframe, as previously explained in *PeriodsForRegr*.

```
extern string   FontNameAndSize          = "Lucida Console,14";
```

Type the name of the font (you must get the spelling exactly correct, for Windows to recognize the font) you want to use, in the displaying of the summary values; then a comma; then the font size you wish to be used.

```
extern color    FontColorBullish         = LimeGreen;
```

If the average slope is greater than 0, then the currency is deemed to be in an uptrend, and the positive summary value will be displayed using the color you select here. Trend traders should be looking to place buy orders, according to their entry rules.

```
extern color    FontColorBearish                    = Tomato;
```

If the average slope is less than 0, then the currency is deemed to be in a downtrend, and the negative summary value will be displayed using the color you select here. Trend traders should be looking to place sell orders, according to their entry rules.

```
extern string   WindowCornerHposVposVspacing = "0,TR,10,250,16";
```

These entries control where the summary table will be displayed on the chart, and its format. You must enter 5 values, separated by commas.

First value is the (sub)window in which you want the values to be displayed. 0 is the main price chart, 1 is the first sub-window below that, 2 is the next sub-window, etc.

Second value is the corner: enter either TL (top left), TR (top right), BL (bottom left), BR (bottom right).

Third value is the starting horizontal pixel number.

Fourth value is the starting vertical pixel number.

Fifth value is the vertical spacing (number of pixels) between each displayed entry (instrument). With a font size of 14, a spacing of 16 allows a small gap (16-14=2) between each row.

```
extern string   Visibility                            = "M1,M5,M15,M30,H1,H4,D1,W1,MN";
```

This controls which timeframe charts the summary will be displayed on. Enter valid values (M1, M5, etc) separated by commas.

```
extern string   OutputFile                           = "PSA.CSV";
```

The indicator can output the same summary that's displayed on screen to a text file. The file could then be read by an EA, and the EA make decisions on which pairs to trade, based on the pair strength values in the file.

If you enter any non-blank text, that will be the name of the file that will be created in MT4's *Files* folder. The file gets overwritten with new values, every time the on-screen values are updated, which is determined by the *RefreshPeriod*.

If you leave the parameter setting blank, then no file will be created.

```
extern bool     ShowCcySummary                     = true;
```

The indicator can also produce a summary of the currencies, which it does by averaging all of the summary values displayed for the pairs. Set this parameter to TRUE to have this summary displayed, or FALSE to disable it.

WINGDINGS SYMBOL CHART

PARAMETER (OR 'PRESETS') FILE

To remove the nuisance of having to retype the same parameter settings every time you attach the indicator to a chart, you have two options. EITHER:

1. Use MT4 templates (but these overwrite any other indicators, objects, etc that you also have on the chart). In this case, the indicator settings are defined when you attach or edit the indicator, using MT4's built-in dialog; OR
2. Use parameter file(s), as follows:
 - If you enter nothing or TXT into the **ParameterFile** setting, then the indicator looks for a parameter file called [Presets---PSA.TXT](#) in the [...../MQL4/Files](#) folder.
 - If you enter any other text (e.g. XXX, 001, etc) into the **ParameterFile** setting, then the indicator looks for a parameter file called [Presets---PSA.XXX](#), [Presets---PSA.001](#), etc in the [...../MQL4/Files](#) folder. (This allows you to set up a different definition in each file, then simply enter the file suffix when you attach the indicator).
 - If the file can't be found, then the settings in MT4's dialog will be used. If the file is found, then the settings in the file will be used instead. Hence if you want to force the use of the MT4 dialog settings, enter the name of a non-existent file (e.g. 'NONE').

Use a text editor like Notepad to view and/or edit the parameter presets files.

To disable an individual entry in the file, start the line with two slashes (//). This means that the setting specified in the MT4 dialog (when you attach/edit the indicator) will be used instead. To re-enable it, remove the slashes. If you have

multiple 'unslashed' entries in the file, the last will be used. You can also disable an entry by setting its parameter value to an asterisk (*). Thus either of

```
// FinalScaleValue = 100;
```

or

```
FinalScaleValue = *;
```

will allow you to adjust the scale via the MT4 dialog, i.e. without the need to edit the parameter file.

You may use any number of embedded spaces or underscores, and/or any combo of upper or lower case, to aid readability, however you wish. The only exceptions are date fields (currently, there aren't any), which must be entered exactly in the form YYYY.MM.DD<space>HH:MM

Every line in the file (including blank lines, and lines beginning with two slashes) MUST end with a semi-colon (;). Failure to do this will cause unpredictable results.

If an entry occurs multiple times in the file, the last occurrence is used to set the parameter value, e.g.

```
FinalScaleValue = 50;
```

```
FinalScaleValue = 100;
```

means that the scaling will be set to 100.

To save typing and improve accuracy, copy/paste the sample lines in the file.

To disable the entire file, either rename it, or delete its content.

To have any changes take immediate effect, either (1) re-attach the indicator to your chart; (2) edit the indicator (press Ctrl-I); (3) switch between timeframes, or (4) switch between currency pairs. Otherwise the chart will not be refreshed/re-plotted until the **RefreshPeriod** setting takes effect.

===== END OF DOCUMENT =====