

```

OneDirectionOnly    = true; // will not allow buy and sell at same time

ExclusiveMode       = false; //will not trade if any other open order is found, either same symbol and different
magic, either other symbol no matter magic

TradeShort          = true; //Allow place sell ordes

TradeLong           = true; //Allow place buy orders

ReverseDirection    = true; // true = will trade long when price is low and short and price is high. false = will trade
long when price is high and short when price is low

Use_MACD            = false;

MacdTF              = 15; // MACD time frame

Fast_EMA            = 12;

Slow_EMA            = 26;

Signal_SMA          = 9;

MACD_Price          = 1; // 0:Close 1:Open 2:High 3:Low 4:Median 5:Typical 6:Weighted

MACD_mode           = 0; // = 0 - default MACD, != 0 - ZeroLag_MACD_v1

MACD_rev            = false;

MoneyMangement      = true; //will autocalculate lot size, lot increment and profit target

MicroAccount        = true; //will divide LotSize by 10

MaximumRisk         = 0.02; // 1 mean 0.1% of balance

//Lots setup

LotMultiplier       = 1; // Must set Multiplier and CounterTrendMultiplier to 1 to use

LotSize             = 0.01; //NULL if MoneyMangement is true

LotIncrement        = 0.02; //NULL if MoneyMangement is true

Multiplier          = 1; // Will increase orders in Martingale fashion in direction of trend if set to "1". Used with
TrendSpacing only.

CounterTrendMultiplier = 1; // Will increase orders in Martingale fashion in opposite direction of trend if set to "1".
Used with Spacing only.

//Profit settings

ProfitTarget        = 1; // All orders closed when this profit target amount (in deposit currency) is reached. set=0 to
disable profit target

IncrementProfitTarget = true; //if true ProfitTarget will increase according to total traded lots

```

ProfitMode = 1; // 1= mixed mode, 2= global mode, 3= split mode

ProfitTrailing = true; // Will try to allow profit grow beyond ProfitTarget

MaxRetrace = 5; // Maximum percent of MaxProfit allowed to decrease before close all orders

  

AutoSpacing = true; //Spacing will be calculated using ATR

ATRTF = 15; // TF for ATR

ATRPer = 7; // length of ATR

MinSpacing = 45; //Minimum spacing for AutoSpacing

TrendSpacing = 75; // Minimum distance of orders placed with the trend of the initial order (set to 1000 to disable )